Helicopter Rig Project

Generated by Doxygen 1.8.13

Contents

1	Mod	fule Index	2
	1.1	Modules	2
2	Data	a Structure Index	2
	2.1	Data Structures	2
3	Mod	dule Documentation	2
	3.1	ButtonsApi	2
		3.1.1 Detailed Description	3
		3.1.2 Enumeration Type Documentation	3
		3.1.3 Function Documentation	3
	3.2	FlightController	5
		3.2.1 Detailed Description	5
		3.2.2 Function Documentation	5
	3.3	HeightApi	6
		3.3.1 Detailed Description	6
		3.3.2 Function Documentation	6
	3.4	HeightController	7
		3.4.1 Detailed Description	7
		3.4.2 Function Documentation	7
	3.5	PidController	9
		3.5.1 Detailed Description	9
		3.5.2 Function Documentation	9
	3.6	PwmOutput	11
		3.6.1 Detailed Description	11
		3.6.2 Enumeration Type Documentation	11
		3.6.3 Function Documentation	11
	3.7	SwitchApi	13
		3.7.1 Detailed Description	13
		3.7.2 Enumeration Type Documentation	13
		3.7.3 Function Documentation	13
	3.8	YawApi	14
		3.8.1 Detailed Description	14
		3.8.2 Function Documentation	14
	3.9	YawController	16
		3.9.1 Detailed Description	16
		3.9.2 Function Documentation	16

4	Dat	a Struct	ure Documentation	19
	4.1	PidSta	te Struct Reference	19
		4.1.1	Detailed Description	19
Inc	dex			21
1	Mo	odule I	ndex	
1.1	M	odules		
He	re is	a list of	all modules:	
	But	tonsApi		2
	Flig	htContr	oller	5
	Hei	ghtApi		6
	Pid	Controll	er	9
	I	HeightC	ontroller	7
	•	YawCon	troller	16
	Pwr	nOutpu	t en	11
	Swi	tchApi		13
	Yaw	Api		14
2	Da	ata Stru	icture Index	
2.1	D	ata Stru	ctures	
He	re ar	e the da	ta structures with brief descriptions:	
		State A struct	ure to accumulate the error and store the previous error for use by the pid controller	19
3	Mo	odule [Occumentation	
3.1	В	uttonsA	pi	
En	umera	ntions		
	В	IUM_BU	ton { BTN_DOWN, BTN_LEFT, BTN_RIGHT, TTONS } the buttons.	

3.1 ButtonsApi

Functions

void ButtonsInit (void)

Initialise the buttons.

• void UpdateButtons ()

Update all of the buttons and their state.

• uint8_t NumPushes (uint8_t button_name)

Gets the number of pushes for a given button and resets the push count.

void ResetPushes (void)

Reset the push count for all buttons.

- 3.1.1 Detailed Description
- 3.1.2 Enumeration Type Documentation

3.1.2.1 Button

```
enum Button
```

All of the buttons.

Enumerator

BTN_UP	The UP button.
BTN_DOWN	The DOWN button.
BTN_LEFT	The LEFT button.
BTN_RIGHT	The RIGHT button.
NUM_BUTTONS	The total number of buttons.

3.1.3 Function Documentation

3.1.3.1 NumPushes()

Gets the number of pushes for a given button and resets the push count.

button_name	One of BTN_UP, BTN_DOWN, BTN_LEFT, or BTN_RIGHT.
-------------	--

Returns

The number of pushes for the given button since this function was last called.

3.2 FlightController 5

3.2 FlightController

Functions

void FlightControllerInit (void)

Initialise the flight controller module.

· void UpdateFlightMode ()

IJ

const char * GetFlightMode (void)

Get a string representation of the current flight mode.

void PriorityTaskInit (void)

Initialise the priority task sequencer.

void PriorityTaskEnable (void)

Enable the priority task sequencer.

void PriorityTaskDisable (void)

Disable the priority task sequencer.

- 3.2.1 Detailed Description
- 3.2.2 Function Documentation

3.2.2.1 GetFlightMode()

Get a string representation of the current flight mode.

Returns

a string representing the flight mode

3.2.2.2 PriorityTaskInit()

```
void PriorityTaskInit (
     void )
```

Initialise the priority task sequencer.

This timer handles updating of the pid controllers and height.

3.3 HeightApi

Functions

• int32_t GetHeight (void)

Get the current height.

int32_t GetHeightPercentage (void)

Get the current height as a percentage.

• void UpdateHeight ()

Trigger the current height reading to be updated.

void HeightManagerInit (void)

Initialise the height sensor peripherals and ports.

void ZeroHeightTrigger (void)

Trigger a zero height reading to be used as a reference for subsequent height readings.

- 3.3.1 Detailed Description
- 3.3.2 Function Documentation

3.3.2.1 GetHeight()

```
int32_t GetHeight (
     void )
```

Get the current height.

Retrieve the sensor reading after it has been offset the zeroed sensor reading.

Returns

The height.

3.3.2.2 GetHeightPercentage()

Get the current height as a percentage.

Returns

The height as a percentage.

3.3.2.3 UpdateHeight()

```
void UpdateHeight ( )
```

Trigger the current height reading to be updated.

No longer used in favour of direct triggering via timer timeout flag.

3.4 HeightController 7

3.4 HeightController

Functions

void SetTargetHeight (uint32_t height)

Set the target height (%).

uint32_t GetTargetHeight (void)

Get the target height (%).

• void HeightControllerInit (void)

Initialise the height controller.

void PreloadHeightController (int32_t control, int32_t error)

Preload the integral component of the pid contoller so the Main rotor starts of with control power.

void UpdateHeightController (uint32_t delta_t)

Update the height controller pid loop.

• void TuneProportionalMainRotor (double gain)

Use at own risk.

3.4.1 Detailed Description

3.4.2 Function Documentation

3.4.2.1 GetTargetHeight()

Get the target height (%).

Returns

The target height(%).

3.4.2.2 PreloadHeightController()

Preload the integral component of the pid contoller so the Main rotor starts of with control power.

This was to improves rise time of the helicopter by boosting the Main rotor.

control	The immediate control power desired by the Main rotor
error	The absolute difference between current height and target height.

3.4.2.3 SetTargetHeight()

Set the target height (%).

Parameters

height The target h	height (%).
---------------------	-------------

3.4.2.4 TuneProportionalMainRotor()

```
\begin{tabular}{ll} {\tt void TuneProportionalMainRotor (} \\ & {\tt double } \end{tabular} \begin{tabular}{ll} {\tt do
```

Use at own risk.

Parameters

gain	Proportial gain.
------	------------------

3.4.2.5 UpdateHeightController()

```
void UpdateHeightController ( \mbox{uint32\_t} \ \ delta\_t \ )
```

Update the height controller pid loop.

delta⊷	The update period of the height controller.
_t	

3.5 PidController 9

3.5 PidController

Modules

- HeightController
- YawController

Data Structures

• struct PidState

A structure to accumulate the error and store the previous error for use by the pid controller.

Functions

void PidInit (PidState *state)

Initialise the pid controller.

void PreloadPid (PidState *state, int32_t integral_preload)

Preload the integral component of the pid state with a postitve or negative error to reduce integration time.

• int32_t UpdatePid (PidState *state, int32_t error, uint32_t delta_t, double proportional_gain, double integral
_gain, double derivative_gain)

Update the pid controller loop.

- 3.5.1 Detailed Description
- 3.5.2 Function Documentation

3.5.2.1 PidInit()

```
void PidInit (
          PidState * state )
```

Initialise the pid controller.

Parameters

```
state The pid error state.
```

See also

PidState

3.5.2.2 PreloadPid()

Preload the integral component of the pid state with a postitve or negative error to reduce integration time.

Parameters

state	The pid error state.
integral_preload	The preload error.

3.5.2.3 UpdatePid()

Update the pid controller loop.

Parameters

state	The pid error state.
error	The current error.
delta_t	The update period of the pid controller.
proportional_gain	The proportional gain constant.
integral_gain	The integral gain constant.
derivative_gain	The derivative gain constant.

Returns

3.6 PwmOutput 11

3.6 PwmOutput

Enumerations

enum PwmOutput { MAIN_ROTOR, TAIL_ROTOR }

An enumeration for determining which PWM output to configure.

Functions

• void PwmInit ()

Initialise both of the pwm outputs.

void SetPwmDutyCycle (uint8_t pwm_output, uint32_t duty_cycle)

Set the duty cycle of the PWM output in the range 2-98%.

uint32_t GetPwmDutyCycle (uint8_t pwm_output)

Get the current PWM duty cycle for the given PWM output.

void PwmDisable (uint8_t pwm_output)

Disable the given PWM output.

void PwmEnable (uint8_t pwm_output)

Enable the given PWM output.

- 3.6.1 Detailed Description
- 3.6.2 Enumeration Type Documentation

3.6.2.1 PwmOutput

```
enum PwmOutput
```

An enumeration for determining which PWM output to configure.

Enumerator

MAIN_ROTOR	The Main rotor PWM output.
TAIL_ROTOR	The Tail rotor PWM output.

3.6.3 Function Documentation

3.6.3.1 GetPwmDutyCycle()

Get the current PWM duty cycle for the given PWM output.

Parameters

pwm_output	The PWM output.
------------	-----------------

Returns

The current PWM duty cycle as percentage.

3.6.3.2 PwmDisable()

Disable the given PWM output.

Parameters

pwm_output	The PWM output to configure.
------------	------------------------------

3.6.3.3 PwmEnable()

Enable the given PWM output.

Parameters

pwm_output	out The PWM output to configure.
------------	----------------------------------

3.6.3.4 SetPwmDutyCycle()

Set the duty cycle of the PWM output in the range 2-98%.

pwm_output	The PWM output to configure.
duty_cycle	The desired duty cycle, in the range 2-98%.

3.7 SwitchApi 13

3.7 SwitchApi

Enumerations

enum SwitchState { SWITCH_DOWN, SWITCH_UP }

An enumeration of the states of the slider switch.

Functions

void SwitchInit (void)

Initialise the switch.

• void UpdateSwitch ()

Update the switch state.

uint8_t GetSwitchEvent (void)

Get the switch event.

- 3.7.1 Detailed Description
- 3.7.2 Enumeration Type Documentation

3.7.2.1 SwitchState

```
enum SwitchState
```

An enumeration of the states of the slider switch.

Enumerator

SWITCH_DOWN	The switch is in the downwards position.
SWITCH_UP	The switch is in the upwards position.

3.7.3 Function Documentation

3.7.3.1 GetSwitchEvent()

Get the switch event.

Returns

DOWN or UP slide of the switch.

3.8 YawApi

Functions

void YawDetectionInit (void)

Initialises the yaw manager.

int32_t GetYaw (void)

Get the current yaw.

• int32_t GetYawDegrees (void)

Get the current yaw.

int32_t GetClosestYawRef (int32_t current_yaw)

Helper function to return the closest yaw such that the helicopter is facing towards the camera.

void YawRefTrigger (void)

Triggers an interrupt to fire when the refernce yaw has been found.

bool YawRefFound (void)

Check if the reference yaw has been found.

- 3.8.1 Detailed Description
- 3.8.2 Function Documentation

3.8.2.1 GetClosestYawRef()

Helper function to return the closest yaw such that the helicopter is facing towards the camera.

Parameters

```
current_yaw the current yaw
```

Returns

the closest reference yaw

3.8.2.2 GetYaw()

Get the current yaw.

Returns

the yaw (notches)

3.8 YawApi 15

3.8.2.3 GetYawDegrees()

```
int32_t GetYawDegrees ( void )
```

Get the current yaw.

Returns

the yaw (degrees)

3.8.2.4 YawRefFound()

```
bool YawRefFound (
     void )
```

Check if the reference yaw has been found.

Returns

true if the yaw reference has been found else false

3.9 YawController

Functions

int32_t GetTargetYawDegrees (void)

Get the target yaw in degrees.

void SetTargetYawDegrees (int32_t yaw)

Set the desired target yaw (degrees).

int32_t GetTargetYaw (void)

Get the target yaw.

void SetTargetYaw (int32_t yaw)

Set the desired target yaw.

void YawControllerInit (void)

Initialise the yaw controller.

void PreloadYawController (int32_t control, int32_t error)

Preload the integral component of the pid contoller so the Tail rotor starts of with control power.

void UpdateYawController (uint32_t delta_t)

Update the yaw controller pid loop.

• void TuneProportionalTailRotor (double gain)

Use at own risk.

- 3.9.1 Detailed Description
- 3.9.2 Function Documentation

3.9.2.1 GetTargetYaw()

Get the target yaw.

Returns

the target yaw.

See also

YawApi for rotation unit.

3.9 YawController 17

3.9.2.2 GetTargetYawDegrees()

Get the target yaw in degrees.

Returns

The target yaw in degrees.

3.9.2.3 PreloadYawController()

Preload the integral component of the pid contoller so the Tail rotor starts of with control power.

Can be used in conjuction with PreloadHeightController to improve the rise time of the helicopter.

Parameters

control	The immediate control power desired by the Tail rotor
error	The absolute difference between current yaw and target yaw.

3.9.2.4 SetTargetYaw()

Set the desired target yaw.

Parameters

yaw	The desired target yaw.
yaw	The desired target yaw.

3.9.2.5 SetTargetYawDegrees()

Set the desired target yaw (degrees).

Parameters

yaw	The desired target yaw (degrees).
, ,	3 , (3 ,

3.9.2.6 TuneProportionalTailRotor()

```
void TuneProportionalTailRotor ( \mbox{double $\it gain $\it )}
```

Use at own risk.

Parameters

```
gain Proportial gain.
```

3.9.2.7 UpdateYawController()

```
void UpdateYawController ( \mbox{uint32\_t} \ \ delta\_t \ )
```

Update the yaw controller pid loop.

delta⊷	The update period of the yaw controller.
t	

4 Data Structure Documentation

4.1 PidState Struct Reference

A structure to accumulate the error and store the previous error for use by the pid controller.

```
#include <pid.h>
```

Data Fields

• int32_t error_previous

The previous error.

• int32_t error_integrated

The accumulated error.

4.1.1 Detailed Description

A structure to accumulate the error and store the previous error for use by the pid controller.

The documentation for this struct was generated from the following file:

• src/pid.h

Index

Button	PreloadPid
ButtonsApi, 3	PidController, 9
ButtonsApi, 2	PreloadYawController
Button, 3	YawController, 17
NumPushes, 3	PriorityTaskInit
	FlightController, 5
FlightController, 5	PwmDisable
GetFlightMode, 5	PwmOutput, 12
PriorityTaskInit, 5	PwmEnable
	PwmOutput, 12
GetClosestYawRef	PwmOutput, 11
YawApi, 14	GetPwmDutyCycle, 11
GetFlightMode	PwmDisable, 12
FlightController, 5	PwmEnable, 12
GetHeight	PwmOutput, 11
HeightApi, 6	SetPwmDutyCycle, 12
GetHeightPercentage	• •
HeightApi, 6	SetPwmDutyCycle
GetPwmDutyCycle	PwmOutput, 12
PwmOutput, 11	SetTargetHeight
GetSwitchEvent	HeightController, 8
SwitchApi, 13	SetTargetYaw
GetTargetHeight	YawController, 17
HeightController, 7	SetTargetYawDegrees
GetTargetYaw	YawController, 17
YawController, 16	SwitchApi, 13
GetTargetYawDegrees	GetSwitchEvent, 13
YawController, 16	SwitchState, 13
GetYaw	SwitchState
YawApi, 14	SwitchApi, 13
GetYawDegrees	
YawApi, 14	TuneProportionalMainRotor
	HeightController, 8
HeightApi, 6	TuneProportionalTailRotor
GetHeight, 6	YawController, 18
GetHeightPercentage, 6	
UpdateHeight, 6	UpdateHeight
HeightController, 7	HeightApi, 6
GetTargetHeight, 7	UpdateHeightController
PreloadHeightController, 7	HeightController, 8
SetTargetHeight, 8	UpdatePid
TuneProportionalMainRotor, 8	PidController, 10
UpdateHeightController, 8	UpdateYawController
	YawController, 18
NumPushes	
ButtonsApi, 3	YawApi, 14
	GetClosestYawRef, 14
PidController, 9	GetYaw, 14
PidInit, 9	GetYawDegrees, 14
PreloadPid, 9	YawRefFound, 15
UpdatePid, 10	YawController, 16
PidInit	GetTargetYaw, 16
PidController, 9	GetTargetYawDegrees, 16
PidState, 19	PreloadYawController, 17
PreloadHeightController	SetTargetYaw, 17
HeightController, 7	SetTargetYawDegrees, 17

22 INDEX

TuneProportionalTailRotor, 18 UpdateYawController, 18 YawRefFound YawApi, 15